
Aqconfig Documentation

Release 1.0

Michael Taxis

Nov 06, 2020

CONTENTS

1 About 3

2 Main interface 5

2.1 Menu and toolbar 5

2.2 Statusbar 7

3 Information tab 9

4 Communication tab 11

5 Miscellaneous tab 13

6 Trigger tab 15

6.1 Trigger (Wikipedia): 15

7 Debug tab 17

8 Values tab 19

8.1 Values 19

9 List tab 23

10 Settings 25

11 Changelog 27

12 Licensing 29

12.1 Disclaimer of Warranty 29

The program edits the configuration for an acquisition tool for Siemens Simatic S7 PLCs. It was written in Python with Tkinter as GUI library. To build the GUI a GUI Builder named PAGE was used.

Homepage <http://www.taxis-instruments.de>

Contact <aqserver at taxis-instruments dot de>

Author Michael Taxis <michael at taxis-instruments dot de>

Copyright of this document:

Copyright CC BY-SA 3.0

Copyright of the program:

Copyright LESSER GNU GENERAL PUBLIC LICENSE 3.0

Please note that soft- and hardware designations and brand names of their respective companies used in this document are generally subject to trademark protection or patent protection.

ABOUT

With this program you can edit configuration files for the data acquisition program aqserver. Its GUI is written in [Python](#) and [Tkinter](#). To build the GUI a GUI Builder named [PAGE](#) was used.

This was my first (finished) Python (3) application with a GUI. I always use my (private) projects to learn something new. Lots of web pages and lots of [Stack overflow](#) entries have been visited to find solutions to my problems. Thanks a lot to the community of coders and developers.

MAIN INTERFACE

2.1 Menu and toolbar



Menu and toolbar show the same functions. left part of the toolbar shows the File menu functions, right part shows the Help menu functions.

1. File

1. New



Clears all fields for a fresh config file

2. Open ...



Opens an existing configuration file

3. Save



Save the open file

4. Save as ...



Lets you save the open file under a new name

5. Settings



Opens a new dialog window, where you can adjust the program settings

6. Save *.bat



Saves a batch file next to the config file, that you can use to start Aqserver directly with this config-file

7. Quit



Closes the configuration program

2. Help

8. Help contents



Opens the help file in a browser

9. Context help



switches the mouse pointer to a arrow with question mark. Click on a element in the interface and help for this element will be displayed in the browser

10. About



Shows an About box for the program



2.2 Statusbar



The statusbar shows the name of the open config file and whether it has been modified

INFORMATION TAB

The screenshot shows the 'Aqserver configuration tool' window. The title bar includes the text 'Aqserver configuration tool' and standard window controls. Below the title bar is a menu bar with 'File' and 'Help'. A toolbar contains icons for adding, saving, editing, and deleting. The main area has a tabbed interface with 'Info', 'Communication', 'Miscellaneous', 'Trigger', 'Debug', 'Values', and 'List'. The 'Info' tab is active, displaying fields for 'Customer:', 'Creator:', 'Machine:', 'Order:', and 'Remarks:'. The 'Remarks:' field is a larger text area. At the bottom, a status bar indicates 'Config file: no file open'.


Customer:	<input type="text" value="name of customer"/>
Creator:	<input type="text" value="your name"/>
Machine:	<input type="text" value="type of machine"/>
Order:	<input type="text" value="order number"/>
Remarks:	<div></div>

Config file: no file open

In this tab we can enter some general information about the data recording, to identify the situation later on

1. **Customer:** here we enter the customers name or some other information
2. **Creator:** enter your name
3. **Machine:** information about the machine (e.g. type, year, machine number)
4. **Order:** enter your order number
5. **Remarks:** enter a description for the recording, e.g. what was the problem, how did you solve it, result

COMMUNICATION TAB




Here we enter the communication details, how to reach the PLC


1. **Demo:** if checked, we run the program in demo mode, no real communication, random values will be created
2. **IP address:** enter the IP address of the PLC
3. **Rack no.:** enter the rack number of the PLC
4. **Slot no.:** enter the slot number for the CPU in the rack, can be found in HW Config of Step7

(0) UR2ALU	
1	PS 405 10A
3	CPU 417-5 H PN/DP
X2	DP
X1	MPI/DP
IF1	
IF2	
X5	PN-IO
X5 P1 R	Port 1
X5 P2 R	Port 2
5	CP 443-1
X1	PN-IO
X1 P1 R	Port 1
X1 P2 R	Port 2
6	CP 443-1(1)
X1	PN-IO-1-1
X1 P1 R	Port 1
X1 P2 R	Port 2
7	CP 443-5 Ext
8	
9	

MISCELLANEOUS TAB



1. **datafile prefix** here you enter the name of the datafile, archives will additionally have a timestamp in the name.
2. **storage path** here you can enter the path where you want the archives to be stored. With the button a dialog will open where you can pick a directory



With this dialog you can select the storage path


3. **use....** With this checkbox you can select whether the archives should be stored under a directory structure by day
4. **scantime** enter the scan interval in milliseconds

TRIGGER TAB


6.1 Trigger (Wikipedia):

In physics, a trigger is a system that controls the data collection of an experiment. Often it is not possible or not important to continuously record all measured values in experiments. In this case only a part of the measured values is read out and based on this, it is decided when the remaining data should be read out.

In our case we use the trigger to start a new datafile.



1. **trigger checkbox:** switch trigger function on or off
2. **trigger signal:** choose the trigger from available signals with the combobox




combobox with trigger signals

3. **trigger condition:** choose the comparison operator for the trigger
4. **trigger value:** value the trigger signal is compared with
5. **pre-trigger:** time before the trigger, where signals will go into new file
6. **post-trigger:** time after trigger, where signals will go into old file

Note: Pre- and post-trigger are used to get an overlap between old and new datafile


DEBUG TAB



1. **Level** select the debugging level (for aqserver), where “1 - INFO” is the most verbose
2. **Files to keep** Give a number of logging files that will be kept.

VALUES TAB

8.1 Values



1. **Area of values** select the area of the value from the following
 - a. **Data** value is from the data area, you have to select also a datablock number and the address
 - b. **Output** value is from the output area, you have to select also the address. Note that datablock number is greyed out.
 - c. **Input** value is from the input area, you have to select also the address. Note that datablock number is greyed out.
 - d. **Flag** value is from the flag area, you have to select also the address. Note that datablock number is greyed out.

- e. **Timer** value is from the timer area, you have to select also the address. Note that datablock number is greyed out. Also the only allowed format is Int 16 bit
 - f. **Counter** value is from the counter area, you have to select also the address. Note that datablock number is greyed out. Also the only allowed format is Int 16 bit
2. **Data block number** enter / select the number of the datablock
 3. **Address** enter the address of the value
 4. **Format** select the format of the value with the radio buttons
 - a. **Real 32 bit** value is a real (float) number , with a length of 32 bit (REAL) Note that bottom notebook switches automatically to the value tab.
 - b. **Dint 32 bit** value is a integer number, with a length of 32 bit (DINT) Note that bottom notebook switches automatically to the value tab.
 - c. **Int 16 bit** value is a integer number, with a length of 16 bit (WORD) Note that bottom notebook switches automatically to the value tab.
 - d. **Int 8 bit** value is a integer number, with a length of 8 bit (BYTE) Note that bottom notebook switches automatically to the value tab.
 - e. **Bool** value is a boolean value (TRUE/FALSE). Note that bottom notebook switches automatically to the bool tab.

8.1.1 Value

The screenshot shows the 'Value' configuration window. It has two tabs: 'Value' (selected) and 'Bool'. The 'Value' tab contains the following fields:

- Name:** A text input field containing the text 'name'.
- Gain:** A numeric spinner field set to 1.0.
- Offset:** A numeric spinner field set to 0.0.
- Unit:** An empty text input field.

On the right side of the window, there is a vertical panel titled 'value functions' containing four buttons: 'Clear', 'Edit', 'Save', and 'Add'.

1. **Name** The name for the value

Note: Names have to be unique. No duplicate entries are allowed in the list!

2. **Gain** The value coming from the PLC is multiplied with this value This can be used if several signals have to be compared but have different range (but maybe the same shape). Leave 1.0 for no effect (default setting).
3. **Offset** This value is added to the result of (value coming from the PLC multiplied by gain) Use this to shift the value up or down. Leave 0.0 for no effect (default setting)
4. **Unit** Enter a unit of the measured value, e.g. m³, bar, psi. . .

8.1.2 Bool

Smallest value that can be read from the PLC is a Byte. So in order to get a boolean value we have to get a byte and then separate it to 8 booleans.

	Name	Gain	Offset
Bit 0	name 0	1	0
Bit 1	name 1	1	0
Bit 2	name 2	1	0
Bit 3	name 3	1	0
Bit 4	name 4	1	0
Bit 5	name 5	1	0
Bit 6	name 6	1	0
Bit 7	name 7	1	0

value functions

Clear Edit Save Add

1. **name for every bit** The name for the bits (also unique)
2. **Gain for every bit** Gain does not make much sense, but we have it anyway. Leave 1 for no effect (default setting)
3. **Offset for every bit** This value is added to the result of (value coming from the PLC multiplied by gain). Can be useful if several boolean values are in one graph, to separate them. Leave 0 for no effect (default setting)


Note: There is no unit for a boolean value

8.1.3 Buttons


1. **Clear** This button clears the entry fields and sets some defaults
2. **Edit** This button switches to the list tab, so you select a value/row for edit
3. **Save** Changes to a selected value will be saved to the list. If no value was selected previously, then button is greyed out
4. **Add** Values entered to the fields will be added to the end of the list

Duplicate names

All value names must be unique. If a name entered to the Name field or to the Name0..7 field for the boolean is already in the list, a dialog will open and show the duplicates. Enter a different name for the shown ones and save/add again.




LIST TAB




1. **Edit** Edit the selected value/row from the list. Will open this value in the values tab
2. **Delete** Deletes the selected value from the list. Has to be confirmed.

Note: Deleting a value from the list can destroy the display of a datafile in KST2, because it is based on the order of the values in the datafiel. When we change the order by deleting a value from the list, then display will not work anymore.

SETTINGS



1. **Button Path to Aqserver.exe** Here we have to select the directory where the Aqserver.exe is located.



Default location is “C:Program Files (x86)Aqserver”

2. **Label Path to Aqserver.exe** The label shows the directory
3. **Language combobox** Select language for the program from the combobox
4. **Ok** Click to accept settings
5. **Cancel** Click to close the dialog and leave previous settings

CHANGELOG

- 05 October 2020
 - 0.1.0alpha
first version

LICENSING

Aqserver is distributed as python source code or Windows setup program under [Lesser General Public License version 3.0 \(LGPLv3\)](#)

Basically this means that you can distribute your commercial software linked with Aqconfig without the requirement to distribute the source code of your application and without the requirement that your application be itself distributed under LGPL.

A small mention to the project or the author is however appreciated if you include it in your applications.

12.1 Disclaimer of Warranty

THERE IS NO WARRANTY FOR THE PROGRAM, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE PROGRAM “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE PROGRAM IS WITH YOU. SHOULD THE PROGRAM PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.

IF ANYONE BELIEVES THAT, WITH THIS WEBSITE OR WITH AQCONFIG PROJECT SOME COPYRIGHTS HAVE BEEN VIOLATED, PLEASE EMAIL US, AND ALL THE NECESSARY CHANGES WILL BE MADE.